



# FlexNet Device Manager for Avid

Administration Guide

## Legal Notices

Product specifications are subject to change without notice and do not represent a commitment on the part of Avid Technology, Inc.

This product is subject to the terms and conditions of a software license agreement provided with the software. The product may only be used in accordance with the license agreement.

This product may be protected by one or more U.S. and non-U.S. patents. Details are available at [www.avid.com/patents](http://www.avid.com/patents)

This document is protected under copyright law. An authorized licensee of [product name] may reproduce this publication for the licensee's own use in learning how to use the software. This document may not be reproduced or distributed, in whole or in part, for commercial purposes, such as selling copies of this document or providing support or educational services to others. This document is supplied as a guide for [product name]. Reasonable care has been taken in preparing the information it contains. However, this document may contain omissions, technical inaccuracies, or typographical errors. Avid Technology, Inc. does not accept responsibility of any kind for customers' losses due to the use of this document. Product specifications are subject to change without notice.

Copyright © 2014 Avid Technology, Inc. and its licensors. All rights reserved.

The following disclaimer is required by Flexera Software, Inc.:

Pages 10-19 in this guide are an excerpt from FlexNet Embedded Server Application User Guide FNE-0400-SAG01. Rights provided by Flexera Software Inc.

## Attn. Government User(s). Restricted Rights Legend

U.S. GOVERNMENT RESTRICTED RIGHTS. This Software and its documentation are "commercial computer software" or "commercial computer software documentation." In the event that such Software or documentation is acquired by or on behalf of a unit or agency of the U.S. Government, all rights with respect to this Software and documentation are subject to the terms of the License Agreement, pursuant to FAR §12.212(a) and/or DFARS §227.7202-1(a), as applicable.

## Trademarks

Avid, the Avid logo, and Digidesign are trademarks or registered trademarks of Avid Technology, Inc. in the United States and/or other countries. See [www.avid.com/US/about-avid/legal-notices/trademarks](http://www.avid.com/US/about-avid/legal-notices/trademarks) for more information on Avid's trademarks.

Adobe and Photoshop are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries. Apple and Macintosh are trademarks of Apple Computer, Inc., registered in the U.S. and other countries. Windows is either a registered trademark or trademark of Microsoft Corporation in the United States and/or other countries. All other trademarks contained herein are the property of their respective owners.

This document is distributed by Avid in online (electronic) form only, and is not available for purchase in printed form.

FlexNet Device Manager for Avid Administration Guide • 0175-30994-00 Rev H • October 2014

# Contents

Before you Begin. . . . .	5
Installing the FlexNet Device Manager for Avid . . . . .	6
Setting Up the FlexNet Device Manager for Avid . . . . .	6
FlexNet Device Manager Setup for Initial Licenses . . . . .	7
Adding Additional Licenses to a FlexNet Server . . . . .	9
Activating Each Client . . . . .	11
Using the Different Views in the FlexNet Device Manager for Avid . . . . .	13
Reservations View in FlexNet Device Manager . . . . .	13
Devices View in FlexNet Device Manager . . . . .	15
Feature Usage View in FlexNet Device Manager . . . . .	16
Properties and Status View in FlexNet Device Manager . . . . .	17
Server Logs View in FlexNet Device Manager . . . . .	19
FlexNet Device Manager Information and Settings . . . . .	20
Configuring a Redundant Floating License Server . . . . .	21
Before You Begin . . . . .	21
System Diagram . . . . .	21
Installing the Redundant Server . . . . .	22
Activating Clients . . . . .	24
Testing the System . . . . .	24
In the Event of Server Failure . . . . .	25



# Installing and Configuring the FlexNet Device Manager for Avid

This document is intended for the Administrator at your facility. The FlexNet Device Manager for Avid is used for large facilities to license, activate and manage concurrent floating licenses for Avid applications which require software activation. Using the FlexNet Device Manager for Avid application on a dedicated Windows server, you can license multiple applications or options.

In addition to the FlexNet Device Manager for Avid, you must activate each client license with the Avid Application Manager. You can activate all or just some of the purchased client licenses using the Avid Application Manager utility

You need to install the FlexNet Device Manager for Avid application on a Windows system. Supported Windows operating systems include: Windows XP SP3 or newer, Windows Server 2003 SP1, or newer. Your Avid editing application can be installed on a Windows or Macintosh system.



**If you are setting up a Floating License server for the first time and are adding a redundant Floating License server, follow the procedures supplied in this document. If you already have a Floating License server and are configuring a redundant Floating License server, contact Customer Care before you attempt to configure a redundant server.**



*Flexnet Device Manager does not currently work with a server that has teamed NIC cards.*



*Some of the screenshots and examples displayed in this guide use Avid Media Composer as the client. You may be activating a different application or option.*

## Before you Begin

Before you install and configure the FlexNet Device Manager for Avid to manage your floating licenses, you should make sure that you configure your network to allow client systems to access the Windows server where you install the FlexNet Device Manager for Avid application.



*You must have ports 3333 and 8888 opened in your Firewall settings.*

The FlexNet Device Manager for Avid application must be installed on a Windows system. However, you can activate the licenses from either a Windows or Macintosh client system.

After you purchase a floating license from Avid, you will be provided with Activation Cards that will provide a System ID and Activation IDs once redeemed.



*The FlexNet Device Manager for Avid application installs on a server that requires an Internet connection to complete the activation procedure.*

## Installing the FlexNet Device Manager for Avid

The FlexNet Device Manager for Avid manages the concurrent use licenses for Avid applications and some options. To use the FlexNet Device Manager, you must install the application on a Windows system server to license and manage your Avid licenses. The server must be viewable by all network clients that will run the software.



*For server access, port 3333 and port 8888 must be open on your Windows server. For more information, see your Firewall settings in your Windows documentation.*

Supported Windows operating systems include: Windows XP SP3 or newer, Windows Server 2003 SP1, or newer.

### **To install the FlexNet Device Manager for Avid application:**

1. Quit all active applications.
2. Navigate to EditingApplicationName\Installers\VolumeLicenseServer in your editing application's installation folder and double-click FlexNetDeviceManagerSetup.exe.

The installation program starts.

3. Follow the prompts to finish the installation.
4. Click Exit.

## Setting Up the FlexNet Device Manager for Avid

After you install the license application on your server, use the FlexNet Device Manager for Avid application to configure the server and activate your Avid software licenses.

The FlexNet Device Manager for Avid has a browser based administration user interface.

The Device Manager supports the following browsers:

- Microsoft Internet Explorer 7.x, 8.x
- Mozilla Firefox 3.x

### The ID's you will need for setup and activation:

- System ID  
Located on the Activation Card you receive when you purchase a floating license. The System ID will also be placed in your Account once you redeem the code. See [Redeeming an Activation Code](#).
- Activation ID  
All Activation IDs will be placed in your account once you redeem the codes from the Activation Cards. See [Redeeming an Activation Code](#).
- Server Host ID  
Your Server Host ID is located on the Properties and Status page in the FlexNet Device Manager application. Go to <http://your server name:8888/FneServer/> and click Properties and Status, and write down the Server Host ID.

If you are performing a first time license installation, follow the procedures in [“FlexNet Device Manager Setup for Initial Licenses” on page 7](#).

## FlexNet Device Manager Setup for Initial Licenses


Perform the following if you are setting up the FlexNet Device Manager for an **initial** license.



**If you are setting up a redundant server, follow the procedure in “Configuring a Redundant Floating License Server” on page 18.**

### To set up the FlexNet Device Manager for Avid (Initial License setup):

1. From any system, go to <http://www.avid.com/license>.  
You will need your System ID, Activation ID and Server Host ID. To obtain these IDs, see [“The ID's you will need for setup and activation:” on page 7](#).  
The Avid Software License Activation Web page opens.
2. In the Software License Activation Web page, enter your Activation ID.  
To locate the Activation ID, see [“The ID's you will need for setup and activation:” on page 7](#).
3. Enter your System ID and then your Server Host ID in the Device ID field.  
To locate the Server Host ID and the System ID, see [“The ID's you will need for setup and activation:” on page 7](#).



4. If you would like to have your Activation file sent to you, enter your e-mail address
5. Click Activate.

The Avid licensing system creates a bin license file. This file contains license information needed to activate your floating license server.


If you entered an e-mail address, the .bin file will be sent to you as an attachment. You can also download the .bin file directly from the site.

6. Click Download to save the .bin file to your system.
7. Locate the .bin file and move the .bin file onto your Server system.
8. From your Server system, go to <http://your server name:8888/FneServer/> (case sensitive).

The FlexNet Device Manager for Avid opens.

9. Under the FNE Server options, click Offline Server Updates.





10. Click the Browse button and locate the .bin file (Upload response file) that you copied onto your Server system, then click Open.
11. Click Upload.

This sets up and activates your floating license server. You can now activate each machine where you have installed the Avid application or options.



*You can verify a successful activation by viewing the Feature Usage page in the FlexNet Device Manager. For more information, see “Feature Usage View in FlexNet Device Manager” on page 16.*

To activate your Avid software application or options, see “Activating Each Client” on page 11.

## Adding Additional Licenses to a FlexNet Server

Perform the following if you have already setup a server and need to add more licenses. When you purchase additional licenses, you will receive an activation card. Use the card to redeem an Activation ID. Once you have redeemed the Activation ID (see [Redeeming an Activation Code](#)), perform the following to add the licenses.

### To add licenses:

1. From any system, go to <http://www.avid.com/license>.

You will need your System ID, Activation ID and Server Host ID. To obtain these IDs, see “The ID’s you will need for setup and activation:” on page 7.

The Avid Software License Activation Web page opens.

2. In the Software License Activation Web page, enter your Activation ID and if you would like to have your Activation file sent to you, enter your e-mail address.

To locate the Activation ID, see “The ID’s you will need for setup and activation:” on page 7.

3. Enter your Server Host ID in the Device ID field and your System ID.

To locate the Server Host ID and the System ID, see “The ID’s you will need for setup and activation:” on page 7.

If you are configuring a Backup server, make sure you enter your Backup Server Host ID as well.

4. Click Activate.

The Avid licensing system creates a .bin. This file contains license information needed to activate your floating license server.

If you entered an e-mail address, the .bin file will be sent to you as an attachment. You can also download the .bin file directly from the site.


5. Click Download to save the .bin file to your system.

6. Locate the .bin file and move the .bin file onto your Server system.

7. From your Server system, go to <http://your server name:8888/FneServer/> (case sensitive).

The FlexNet Device Manager for Avid opens.

8. Under the FNE Server options, click Offline Server Updates.



9. Click the Browse button and locate the .bin file (Upload response file) that you copied onto your Server system, then click Open.
10. Click Upload.

The additional licenses are added to the server.



*You can verify a successful activation by viewing the Feature Usage page in the FlexNet Device Manager. For more information, see “Feature Usage View in FlexNet Device Manager” on page 16.*

To activate your Avid software application or options, see “Activating Each Client” on page 11.

## Activating Each Client

Use the Avid Application Manager to activate the licenses for each Avid software application and options. Repeat these steps for each client or option you are activating.


### To activate each Avid software application:

1. To activate an Avid software application, install and launch the application on each machine.

The Welcome window opens.



2. Click “I want to activate my software using the Internet, another computer, or a floating license server” under the Electronic Activation section.
3. The Application Manager opens.



4. Select Floating from the Select Activation method menu.
5. Enter your Floating License Server URL, then click Save.  
The Application Manager confirms your system information.  
If applicable, enter the Backup Server URL, then click Save.
6. Quit out of the Application Manager utility and the editing application will continue to launch via the Floating License.
7. To confirm this activation, you can go to the FlexNet Device Manager, and click the Devices tab.

The system displays the Device ID and device alias of each activated client.

You can also checkout a floating license if you want to work on your system while not being connected to the Internet. This might be useful if you are working on a laptop and then want to take the laptop home to finish working on your project. For details on checking out a floating license, search for “Checking Out a Floating License” in the [Installation Guide for Avid Editing Applications](#).

## Using the Different Views in the FlexNet Device Manager for Avid

The following sections are excerpts from Flexera™ Software Inc.

These are optional features you can use to manage your floating license:

- Reserving new entries and modifying entries on your server
- Viewing information on reserved devices
- Viewing details regarding every feature in the counted pool including overage information
- Upload Response views to enable you to update the server license pool using offline operations
- Display the Properties and Status view with the current settings used by the server application
- Display log information about the server
- Display Device Manager information and settings

### Reservations View in FlexNet Device Manager

The FlexNet Device Manager software allows the administrator to set activation reservations for specific users or devices. Using a reservations list, the administrator can define a specified quantity of a feature or features in a pool to be available to a specific device. In essence you are allocating an activation from the license pool and reserving it for a device with a specific host id.

The Reservations View enables viewing and modifying entries in your server's reservation list.



The Reservations view displays the contents of the current reservation list. The notation in the Status column indicates whether license rights exist to fulfill the reservation. The green check mark indicates that a reservation can be satisfied, and the red cross indicates a reservation that cannot be satisfied.

### To add a reservation:

1. Click Add to add a single reservation to the reservation list.

The Add Reservation page opens. If a reservation list does not yet exist, it will be created in the server's configured XML cache location as a file named reservations.xml.

**FlexNet Device Manager**

**Add Reservation**

• **Device ID:**   
Unique alphanumeric string, without spaces, that identifies the client device.

**ID Type:**   
ID type of the client device.

**Device Type:**   
Type of device.

**Device Alias:**   
User-friendly name for the device.

• **Feature Name:**   
Name of feature.

• **Version:**   
Feature version. Example: 1.0 or 2.12

• **Count:**   
Number of features to be reserved for the device.

• = Required field.

2. Enter the required fields.

The Device ID refers to the client needing a reserved license. You can locate the Feature Name and Version in the Devices View (see [“Devices View in FlexNet Device Manager” on page 15](#)).

3. Click Add to add the reservation to the reservation list.

Click Cancel to reset the current entry values without saving.

4. Click Edit in the Reservations view to modify the reserved count of a particular device–feature combination in the reservations list.

Changing a feature’s count to 0 (zero) removes the reservation entry from reservations.xml and from the Reservations view.







5. When finished editing, click Submit to finalize the changes and apply them to the server system.



*You can Export the list of reservations and Import on the backup server to save time rather than entering each reservation again.*

## Devices View in FlexNet Device Manager

The Devices view displays the devices recognized by the server application from having fulfilled licenses from the counted pool or from having reservations defined. The name displayed for a device in the Device Alias column is set in the device code using FlxPublisherSetDeviceName.

Devices			
Devices with features consumed or reserved. Click a device ID for further details.			
Device ID	Device Alias	Device Type	Consumed For
 2342811483970441015273855	AvidBeta-MacPro32.local		ENT_MEDIA
 2390371838568432544416727	MacPro i10.9		
 5298058327608568259086474	Betalab-z800	z800 CPU	
 5379344763235271264386693	Betalab-3800	z800 CPU	
 5432385272513217889080072	betalab-z400		ENT_MEDIA
 5437674441468290697754693	Burl-Txjodin7	Win7	
 5437674441468290697754693	txjodin7	Win7	
 5438729968696451044118793	Goro	Win7	

Page 1

**To use the Device View:**

1. Click a Device ID in the Device ID column.

The device's details display, including information about its consumed features and reserved features.

2. Use the Search field to search for a device by its hostid.
3. Click the Device ID header to sort the devices table.



## Feature Usage View in FlexNet Device Manager

The Feature Usage view displays details regarding every feature in the counted pool served by the server application. The Search field enables searching by feature name or version, and features can be sorted by name, version, or count by clicking the column header.



FlexNet Device Manager

## Feature Usage

Search (case-sensitive):  Search by: Feature  

**Features** **Overage**

Features served to or reserved for devices. Click a feature name for usage details.

Feature	Version	Count	Available	Expiry
<a href="#">ENT_MEDIA_COMPOSER</a>	6.0	3	2	permanent
<a href="#">ENT_MEDIA_COMPOSER</a>	6.0	5	5	permanent

Page 1

Copyright (c) 2010-2011 Flexera Software Inc. All rights reserved

Clicking a feature name displays detailed information about the devices currently consuming features from the counted pool and those reserving a given feature.

## Properties and Status View in FlexNet Device Manager

The Properties and Status view displays the current settings used by the server application. With the exception of settings related to security and server policy—borrow interval, renew interval, response lifetime, failover maintenance interval, whether server synchronization to FNO is enabled—settings can be edited in this view. Any changes made in this view take effect when you click Save at the bottom of the page. Properties that additionally require the server—the launcher executable—to be restarted before taking effect are denoted with a restart icon.

Property	Value	Description
Server host ID	00215A2AEB9C (ETHERNET)	Server's host ID used when fulfilling requests registered with the back-office server.
<b>General properties</b>		
Listen TCP/IP address(es)	0::0:0:0:0:0	Semicolon-separated list of IPv6 and IPv4 addresses.
Listen port	3333	Port number (Range: 1-65535) for listening.
Back-office server	localhost	Host name or IP address of the back-office server.
Back-office server port	8080	Back-office server port number (1-65535).
Back-office server endpoint	/request	Back-office server URI where requests are sent.
Refresh interval	600	Refresh interval (in seconds). Minimum is 60.
XML access permission	Remote	Simple security setting indicating permission for remote systems, while "Local" restricts access to local systems only.
Server name		Current server name. Used only for display purposes.
HTTP session timeout	300	Amount of time (in seconds) this server waits for a client to respond.
Server info usage enabled	No	Is server info usage enabled?
Virtual clients enabled	Yes	Indicates whether this FNE server supports virtual clients.
Virtual host enabled	Yes	Indicates whether this FNE server can act as a virtual host.

The properties exposed on this page include:

- **Server host ID:** the server application's hostid value used to fulfill capability requests against a back-office server. If the server has multiple hostid values, the list contains the available hardware Ethernet addresses and dongle IDs; select the value registered with the back-office server.
- **General properties:** this category contains settings such as the port number the server application uses to listen to requests from devices (by default 3333); the back-office server's hostname or IP address, port number, and type; and how frequently the server application refreshes its license rights. Also included in this section is the option to select Remote or Local for the XML access permission. The XML access permission has to be set to Remote to allow activation from external systems.



*If you modify the Listen Port setting here, you must also modify the FNE Server Listen Port setting in the User Interface Configuration view.*

- **FNO poll properties:** indicate whether and how often the server application contacts the back-office server (such as FlexNet Operations), and how often to retry communications after a failed attempt.
- **Synchronization properties:** exposes different types of server synchronization properties.
- **Failover properties:** information about the main and backup servers, if using server failover. This section can be hidden using the Device Manager Settings view.
- **Security properties:** read-only information about the security-policy settings borrow interval, borrow granularity, renew interval, and response lifetime.

- Error log properties: external destination (if any) and log levels to include in the server application's FNE error log. Selecting "File" as the log destination results in additional prompts for log rotation policy settings. Note that the error log location is defined in the value of the error-log/log-directory element in properties.xml, and not exposed in this view.
- Access log properties: external destination (if any) for the Device Manager's HTML access log. Selecting "File" as the log destination results in additional prompts for log rotation policy settings.

The server application's configuration settings are stored in the server's cache file properties.xml. In demo mode, this file is expected to be in the same directory as the launcher executable; in production mode, the directory containing properties.xml is defined in the configured cache location.

This view also provides a Status tab that displays information about the server application, including its version, status, failover role, and last attempted contact and last successful contact with the back-office server.


## Server Logs View in FlexNet Device Manager

The Server Logs view shows two logs related to the server application:

- For file destinations, you can select the desired log file to view from the Log Files drop-down list.

The Error Log tab shows the server application's log file, which includes messages generated by the server application. Which messages are displayed in this log depend on the log levels enabled in the "Log level" selections in the server properties. (For performance reasons, debug-level messages are not displayed in the Device Manager's Error Log tab if the "Log destination" is set to "stderr" or "stdout", even if enabled in the log-level settings. Debug-level messages are of course written to the actual target log destination.)

- The Access Log tab (not pictured) shows standard web-server access information.



## FlexNet Device Manager Information and Settings

Below the other commands in the FlexNet Device Manager menu is the Device Manager group, which contains the About and Settings views. The About view displays build, system, and browser information. In the Settings view, you specify the port number and host name where the FNE server application is running, as well as whether to enable certain Device Manager functionality. These configuration settings appear in a separate list because they can be modified even if the server application is inaccessible, unlike the other server configuration properties.

The properties include:

- Number of log lines: the number of lines of an error or access log file to display per page
- Allow device drop: whether a device's details page should enable the functionality to mark a device as destroyed
- Page size: the number of records to display per page
- FNE server listen port: the port number on which the Device Manager will listen for server application data (default is 3333)
- FNE server host name: the hostname of the system on which the server application executable is running (default is "localhost")
- Display failover properties: whether to display failover-related properties in the Properties and Status view

# Configuring a Redundant Floating License Server

The FlexNet Device Manager for Avid is used for large facilities to license, activate and manage concurrent floating licenses for Avid applications which require software activation. Using the FlexNet Device Manager for Avid application on two dedicated Windows servers, you can license multiple applications or options with high availability.

## Before You Begin

The following equipment is needed:

- Two Windows Servers. Supported Windows operating systems include: Windows XP SP3 or newer, Windows Server 2003 SP1, or newer
- One or more systems for running Avid Software Applications (Mac or Windows)
- An Administrator console (any computer connected to the Intranet)

The redundancy scheme for the FlexNet Device Manager is active/passive. One of the Windows servers will be designated the main server, and the other will be designated the backup server. Both servers will have the same licensing software installed, but be configured differently.

## System Diagram

The following diagrams show how the system will operate in both the normal and failover modes of operation.

Figure 1 shows the normal mode of operation. The editing systems connect to the main licensing system to activate floating licenses.



Figure 1 Normal Mode of Operation

Figure 2 shows the failover mode of operation. The editing systems connect to the backup licensing system to activate floating licenses.








Figure 2 Normal Mode of Operation

## Installing the Redundant Server

Use the following instructions to configure the redundant floating license server. Note that the server names main-server and backup-server should be replaced with the actual names of your servers.

### To configure a Redundant Server

1. Follow the instructions [“Setting Up the FlexNet Device Manager for Avid” on page 6](#). Perform the setup for both the primary and backup servers. Once you perform those steps, return to this procedure and perform steps 2 through 7.
2. On the main server, make the following changes on the Properties and Status Page settings:
  - a. Browse to `http://main-server:8888/FneServer/serverProperties_view.action`
  - b. Sync to FNE enabled: Yes
  - c. Select Save.
  - d. Sync to FNE backup server URI: `backup-server:3333/fne/bin/sync`
  - e. Main server URI: `main-server:3333/fne/bin/capability`
  - f. Backup server URI: `backup-server:3333/fne/bin/capability`

Sync to FNE properties		
Sync to FNE enabled	<input checked="" type="radio"/> Yes <input type="radio"/> No 	Select Yes to synchronize this FNE server's license distribution state to a backup FNE server.
Sync to FNE interval	<input type="text" value="300"/> 	How often, in seconds, server sends synchronization messages to backup FNE server.
Sync to FNE page size	<input type="text" value="100"/>	Number of deduction records to include per synchronization message to the backup FNE server.
Sync to FNE retry count	<input type="text" value="4"/>	Number of times to retry sending synchronization messages to backup FNE server after a failed attempt.
Sync to FNE retry interval	<input type="text" value="300"/>	Interval, in seconds, between attempts to re-send synchronization messages to backup FNE server after a failed attempt.
Sync to FNE backup server URI	<input type="text" value="backup-server.global.avi"/> 	If using sync to FNE, backup server in format "server:port/fne/bin/sync".
Failover properties		
Main server URI	<input type="text" value="main-server:3333/fne/bin"/> 	If using failover, main server in format "server:port/fne/bin/capability".
Backup server URI	<input type="text" value="backup-server:3333/fne"/> 	If using failover, backup server in format "server:port/fne/bin/capability".

3. Click Save.
4. On the backup server, make the following changes on the Properties and Status Page settings:
  - a. Browse to [http://backup-server:8888/FneServer/serverProperties\\_view.action](http://backup-server:8888/FneServer/serverProperties_view.action)
  - b. Sync to FNE enabled: No
  - c. Main server URI: main-server:3333/fne/bin/capability
  - d. Backup server URI: backup-server:3333/fne/bin/capability

Sync to FNE properties		
Sync to FNE enabled	<input type="radio"/> Yes <input checked="" type="radio"/> No 	Select Yes to synchronize this FNE server's license distribution state to a backup FNE server.
Failover properties		
Main server URI	<input type="text" value="main-server:3333/fne/bin"/> 	If using failover, main server in format "server:port/fne/bin/capability".
Backup server URI	<input type="text" value="backup-server:3333/fne"/> 	If using failover, backup server in format "server:port/fne/bin/capability".

5. Click Save.
6. Restart the services on both machines:
  - a. Either directly or by remote access, log onto the machine.
  - b. Right-click on the Task Bar and choose Task Manager

- c. Click on The Services Tab
- d. Right-click to stop then start the following two services:
  - FlexNetDeviceManager
  - FNEServer

FlexNetDeviceManager	860	Apache Tomcat FlexNetDeviceManager	Running
FNEServer	6320	Avid FlexNet Device Manager	Running

- 7. Note the System ID, Activation ID, and BOTH Server Host IDs and follow instructions on [“FlexNet Device Manager Setup for Initial Licenses” on page 7](#). Then return to perform step 8.
- 8. Load the .bin files onto the two servers using the instructions [“FlexNet Device Manager Setup for Initial Licenses” on page 7](#), starting from step 7.

On the Status tab of Properties and Status the main server is set to Failover role of main and the backup server is set to the role of backup.

[http://main-server:8888/FneServer/serverStatus\\_view.action](http://main-server:8888/FneServer/serverStatus_view.action)

Failover role	main	If failover is enabled, indicates whether this server is the main or backup server.
---------------	------	---

[http://backup-server:8888/FneServer/serverStatus\\_view.action](http://backup-server:8888/FneServer/serverStatus_view.action)

Failover role	backup	If failover is enabled, indicates whether this server is the main or backup server.
---------------	--------	---

## Activating Clients

Follow [“Activating Each Client” on page 11](#) to activate the clients.

## Testing the System

To test the system, shut down the main server, and activate a client while just the backup-server is running. You can use the Feature Usage View to check to make sure the backup server is working properly. Be sure restart the main server once the test is done.



## In the Event of Server Failure

In the event of either planned maintenance or system failure, the Avid software will automatically switch to the backup server. Once the main server is back up and configured properly, the Avid software will default back to it. Refer to Figure 2 to see a diagram of the failover mode. If the main server is in need of replacement, please contact Customer Care as its license will need to be deactivated from the original server before it can be applied to a new one.